

cf/x  
Dynamic Mission Library  
for DCS

# DML

## QUICK REFERENCE

### ME MODULE INTEGRATION

Copyright © 2022 by cf/x AG and Christian Franz

# Table Of Contents

1	ME FLAG INTEGRATION .....	4
2	DEBUGGER.....	9
3	Artillery Zones .....	11
4	Artillery UI.....	13
5	baseCaptured.....	14
6	Cargo Receiver .....	15
7	Changer .....	16
8	CivAir.....	18
9	Clone Zone.....	20
10	Count Down.....	23
11	CSAR Manager .....	25
12	Delay Flags .....	27
13	Delicates .....	28
14	FARP Zones.....	30
15	Group Tracker .....	31
16	Guardian Angel .....	33
17	Helo Troops.....	35
18	Impostors .....	36
19	Limited Airframes .....	38
20	Map Markers .....	40
21	Messenger .....	41
22	NDB .....	43
23	Object Destruct Detector .....	45
24	Object Spawn Zones .....	46
25	Owned Zone.....	48
26	Persistence .....	50
27	Player Score.....	52
28	Pulse Flags .....	53
29	Radio Menu .....	55
30	Radio Trigger.....	58
31	Raise Flag .....	59
32	Recon Mode.....	61
33	rnd Flags .....	64
34	Smoke Zones .....	66
35	Spawn Zones .....	67

36	unGrief .....	70
37	Unit Persistence .....	72
38	Unit Zone.....	73
39	Wiper.....	75
40	xFlags (Flag Testing).....	77
41	Module Name .....	79

# 1 ME FLAG INTEGRATION

## 1.1 Understanding DML Flags

A DML module has two independent methods to communicate:

- The way it *sends* signals (the **output method**, usually designated by the exclamation point "!" at the end of the attribute's name). It describes what is sent when the module wants to convey information. This can be 'inc' (the most common, increases the flag's value), or 'On', 'Off', 'flip', a fixed value etc. **A module sets an output flag whenever it sees fit**, usually as a response to something happening in the mission (a group enters a zone, an object is destroyed etc)
- The way a module *receives* signals: how it looks at their inputs (flag attributes with question mark "?" in their name) and tries to decide if it should trigger. Most common is the 'change' method: the module triggers when the flag's current value changes.

### Note:

**Modules look at their input flags regularly**, usually once a second (usually set globally for the module with the ups attribute in the config zone). This means that they do not immediately detect a signal/change, *only the next time they look at their input flags*. This means that they can even miss a signal if the input flag changes too quickly.


## 1.2 Bang! Method (output, sending signals)

DML understands the following methods, each defined by a keyword:

- 'on'  
Sets the flag's value to one, no matter what it was before. Same as using the number 1 (one)
- 'off'  
Sets the flag's value to 0 (zero), no matter what the value was before. Same as using the number 0 (zero)
- 'inc'  
Increases the flag's value by 1 (one). If, for example, the flag's value was previously 10, that is increased to 11
- 'dec'  
Decreases the flag's value by 1 (one). If, for example, the flag's value was previously 10, this number is decreased to 9.
- 'flip'  
This is one of the most effective methods to trigger on flag change. It flips the flag's value between 0 (zero) and "not 0": If the flag's value was anything except zero, the new value is zero. If the flag's value was zero, the new value is 1 (one). This way you

can flip-flop flags, turning them on and off repeatedly.

- (number)  
Sets the flag to the fixed value (number), no parentheses. Example: 33 – sets the flag's value to (the number) 33
- 'pulse' or 'pulse, <number>'  
“pulses” the flag by setting its value to 1 (one) for some time, and then re-setting it to 0 (zero) some time later. If you do not specify any time, the flag is reset after three (3) seconds. You can supply your own pulse time by adding a comma and a number, e.g. “pulse, 4” will keep the pulse up for four (4) seconds before dropping back to zero.



### 1.3 Multiple Output Flags

DML has the ability to bang! multiple flags at the same time. Unless otherwise specified, all output bang! flags (those that end on an exclamation point “!”) support this ability. To bang! multiple flags, they need to be listed as the attribute's value and are separated by a comma; leading/trailing blanks are ignored.

counterOut!	*cVal
tMinus!	*counted
zero!	isZero, startStageTwo

Please note the following:


- All flags are banged with the same method
- All flags are set simultaneously, meaning that there is no guaranteed order in which they are changed.

### 1.4 DML? Watchflag Method (input, receiving signals)

DML understands the following conditions to look for in a flag, each defined by a keyword. Watchflags are inspected regularly and can only trigger after a flag's value changes; they trigger when the following conditions are met:

- 'change' or '#'  
triggers whenever the flag's value changes
- 'off' or '0' or 'no' or 'false'  
triggers when the flag's value changes to zero
- 'on' or '1' or 'yes' or 'true'  
triggers when the flag's value changes from zero to non-zero

(Warning: DML will not detect a transition between two non-zero numbers e.g., 3→4, it only triggers on a change from ZERO to a non-zero value)



- `'inc'` or `'+1'`  
triggers when the flag's value changes to exactly the flag's previous value plus one
- `'dec'` or `'-1'`  
triggers when the flag's value to exactly the flag's previous value minus one
- `'lohi'`  
triggers when the Watchflag's previous value was zero (0) or less and the new value is greater than zero. Often used with the pulse method.
- `'hilo'`  
triggers when the Watchflag's previous value was greater than zero (0) and the new value is zero or less. Often used to detect a countdown reaching zero.
- `'>(number)'` or `'>(name)'`  
triggers when the flag's value changes, and the value is larger than the number given or flag identified by name

**Examples:**

- `>4` triggers when inFlag is larger than the number 4
  - `>*landings` triggers when inFlag is larger than the value of local flag 'landings'
- `'=(number)'` or `'=(name)'`  
triggers when the flag's value changes, and the value is equal to the number given or flag identified by name

**Examples:**

- `=4` triggers when inFlag is equal to the number 4
  - `=*landings` triggers when inFlag is equal to the value of local flag 'landings'
- `'<(number)'` or `'<(name)'`  
triggers when the flag's value changes, and the value is less than the number given or flag identified by name

**Examples:**

- `<4` triggers when inFlag is less than the number 4
  - `<*landings` triggers when inFlag is less than the value of local flag 'landings'
- `'#(number)'` or `'#(name)'`  
triggers when the flag's value changes, and the value is not equal to the number given or flag identified by name

**Examples:**

- `#4` triggers when inFlag is not equal to the number 4
  - `#*landings` triggers when inFlag is not equal to the value of local flag 'landings'

### **Quoting Numbered Flags**

Early versions of DCS used only numbers for flag names. For example, "22" was (and still is) a legal flag name. This can create confusion when using Watchflags as it can't tell the difference between a number and a flag whose name happens to be a number.

In order to allow DML to distinguish between a number and flag whose name happens to be a number, such a flag's name must be put into double quotes "" and "'" to be interpreted as a flag number. Hence, if you want to trigger only if the input flag was equal to flag named 22, the condition would be

= "22"

DML then (and only then) recognizes "22" as meaning the flag named 22 rather than the number 22.

## 1.5 DML Flag Naming Rules

	ME	DML	DML Zone-Local
<b>Format</b>	Positive Number	Alphanumeric, must not contain comma ',', <b>must not start with asterisk '*'</b> , <b>double quote ""</b> or <b>digit ('0'...'9')</b>	<b>Starts with asterisk '*'</b> , alphanumeric, must not contain comma ','
<b>Examples</b>	123 99 2898	A12 With blank F***d up Yup "quotes" too	*1 *A12 *fireCloner *ok multi **
<b>Scope / Visibility</b>	Entire DCS	DML modules, Lua Scripts	Only DML modules in same zone
<b>Invisible to</b>		ME Triggers	Everyone outside Zone



## 2 DEBUGGER

### 2.1 Summary

Interactive (in-mission) debugger utilizing a 'console' via the Add Map Mark Label' mission feature to give commands. Commands start with a hyphen.



and will elicit a response when accepted

```
[08:00:20] flag <kills> : value <0>
```

### 2.2 Dependencies

The debugger requires dcsCommon and cfxZones

### 2.3 ME Integration

Name	Description
debug?	List the flag names that the debugger is to observe. All flags listed here are accessible from the debugger under the observer with the same name as the trigger zone  <b>MANDATORY</b>
triggerMethod debugTriggerMethod inputMethod sayWhen	Trigger condition for the flags (the observer's "condition" that triggers a report for the flag) Defaults to 'change'
method outputMethod debugMethod	DML Method for the debugger's output flags. Rarely used. Defaults to "inc"
notify!	DML flag to bang! when a flag listed in debug? triggers
debugMsg	Message to output when a flag listed in debug? triggers. Supports wildcards, including <f> for the flag name that triggered, and <z> for the zone name.  <b>Note that this allows you to provide individual message formatting per observer</b> , a feature that is not available for the interactive debugger.  Defaults to "---debug: <t> -- Flag <f> changed from <p> to <c> [<z>]" which results in a message similar to <pre>---debug: 08:00:12 -- Flag t1 changed from 2 to 4 [many flags]</pre>

**Supports DML Flags**

**Supports Watchflags**

**Supports zone-local verbosity**

## **2.4 Demos**

- Bug Hunt

## 3 Artillery Zones

### 3.1 Summary

Simulates an artillery barrage inside the zone.

### 3.2 Dependencies

dcsCommon, cfxZones

### 3.3 ME Integration

Name	Description
artilleryTarget	Marks this zone as an artillery zone. Value is ignored <b>MANDATORY</b>
coalition	Used with Artillery UI – the coalition that can give a fire command (the explosions are completely coalition agnostic – they kill anyone). When the artillery zone is marked on the map, only this side will see it. Defaults to 0. Supports “red” and “blue” as values
spotRange	Used with Artillery UI – the maximum range at which an FO can give a fire command. Measured from center of zone. Defaults to 3000 meters
shellStrength	Average power of <b>each</b> exploding shell. Defaults to 500. 3000 is enough to level big buildings, so be conservative.
shellNum	Number of shells (salvo) per fire cycle. Defaults to 17 shells per cycle
transitionTime	The time (in seconds) the shells take on average to reach the target zone. Note that not all shells arrive at once but are usually spread over a couple of seconds. Defaults to 20
addMark	Add the artillery target zone to the F10 map of coalition (see above). Defaults to <b>true</b> .
shellVariance	Difference in shell’s explosion power, in percent. Defaults to 0.2 (20%)
f? in? artillery?	<b>DML Watchflag</b> . When triggered, the artillery bombardment starts. Defaults to <none> You can use any synonym, but only one per zone
triggerMethod artyTriggerMethod	Defines the trigger condition for the DML Watchflag. Defaults to “change”
cooldown	Used with Artillery UI: Number of seconds before the next fire cycle can be initiated. Is ignored when initiating fire via ME flags. Defaults to 120 (= 2 Minutes)
baseAccuracy	The radius (in meters) around the center of the zone in which the projectiles will land. Defaults to the ME zone’s radius (meaning all projectiles will land inside the zone if this attribute is missing and fire cycle is invoked via trigger flag)
silent	Used with Artillery UI: if true, suppresses communication responses from artillery

**Supports DML Flags**

**Supports Watchflags**

### **3.4 Demos**

- Artillery with UI
- Artillery zones triggered
- Pulsing Fun

## **4 Artillery UI**

### **4.1 Summary**

Provides forward observation features for helicopters, along with a UI to trigger artillery zones.

### **4.2 Dependencies**

Tcb

### **4.3 ME Integration**

Tbc

### **4.4 Demos**

- Artillery with UI

## 5 baseCaptured

### 5.1 Summary

This module generates a signal on the output flags when a base (Airfield, FARP, Ship) is captured (note that currently, ships cannot be captured).

### 5.2 Dependencies

dcsCommon, cfxZones

### 5.3 ME Integration

<b>baseCaptured!</b>	Marks this zone as a baseCaptured zone. It lists the flags that should be banged! when the closest base (FARP, Airfield, Ship with Helipad) to this zone is captured by another faction.  <b>MANDATORY</b>
method captureMethod	DML method for output flags Defaults to 'inc'
blueCaptured! blue!	Flags to bang! when blue faction captures the closest base to this zone Defaults to <none>
redCaptured! red!	Flags to bang! when blue faction captures the closest base to this zone Defaults to <none>
contested!	Flags to bang! when closest base becomes contested and belongs to neither blue nor red Requires handleContested be true in configuration (default) Defaults to <none>
baseOwner	Flag that is set by the module to the current faction (0 = neutral, 1 = red, 2 = blue, 3 = contested) that currently holds this base.

**Supports DML Flags**

**Supports zone-local verbosity**

### 5.4 Demos

- Count Base's Blues

## 6 Cargo Receiver

### 6.1 Summary

A zone designed to generate an event / signal on a flag when cargo is landed in the zone. Cargo must be registered with CargoManager

### 6.2 Dependencies

dcsCommon, cfxZones, cfxPlayer, cfxCargoManager.

### 6.3 ME Integration

cargoReceiver	Marks this zone as a cargo receiver zone. Value is ignored <b>MANDATORY</b>
autoRemove	Delete any object <removeDelay> seconds after it was successfully delivered. This is helpful for most ObjectSpawnZones set-ups to trigger their spawn cycle
silent	Set to true to turn off this zone's directions. Defaults to false (zone will talk to pilots)
method cargoMethod	Standard DML flag method for output. Defaults to "inc"
f! cargoReceived!	The flag to bang! when the object is destroyed. Use only one synonym per zone.
removeDelay	The delay (in seconds) after which after a successful delivery an object should be removed. Requires that autoRemove be set to true. Defaults to 1, Minimum is 1

### Supports DML Flags

### 6.4 Demos

- Helo Cargo

## 7 Changer

### 7.1 Summary

This module provides a convenient way to transform flags on-the-fly, and to provide a flexible gated switch

### 7.2 Dependencies

dcsCommon, cfxZones

### 7.3 ME Integration

Name	Description
change?	The input flag whose value is used to create the output signal  <b>MANDATORY</b>
out! changeOut!	The output flag.
triggerMethod triggerChangeMethod	Watchflag method that is used to interpret change? when inEval is set to true Defaults to 'change'
inEval	When set to true, the input flag change? is interpreted as a watchflag under triggerChangeMethod's rules Defaults to false
changeTo to	Operation to apply to the input flag to create the output value. The following operations are defined: <ul style="list-style-type: none"><li>• 'bool' Output value is 0 if input is 0, 1 otherwise (conversion to bool)</li><li>• 'not' Output value is 1 if input is 0, 0 otherwise</li><li>• 'sign' Output value is -1 if input is &lt;0, 1 otherwise</li><li>• 'abs' Output value is the absolute of input value (e.g. outputs '3' for '-3' and '3')</li><li>• 'negative' Output value is input value multiplied by -1, turning the sign.</li><li>• 'direct' Output value is the same as input value. Used primarily with when changer is functioning as a gated switch</li></ul> Defaults to "direct"
min	When defined, ensures that the output value has this value at minimum
max	When defined, ensures that the output value has this value. If max is less than min, output is always set to max



<b>Name</b>	<b>Description</b>
paused changePaused	When set to true, the changer starts in paused/off mode and the output flag is not changed. The only way to turn a paused changer on when off/paused is via a signal on the changeOn? input Defaults to false.
on? changeOn?	Turns a paused changer on, enabling transmission of the input signal (after processing) to output, opening the 'gate'. Triggers on "change" Defaults to <none>
off? changeOff?	Turns a changer off, pausing it. Input signals are no longer processed nor propagated to output, closing the 'gate'. Triggers on "change". Defaults to <none>
On/Off? changeOn/Off?	Flag that when defined controls transmission of input to output when the changer is running (i.e. not paused). The value of this input controls the gate as follows: <ul style="list-style-type: none"> <li>• 0: gate closed, no transmission</li> <li>• Anything else: gate open.</li> </ul> Defaults to <none>

**Supports DML Flags**  
**Supports Watchflags**  
**Supports zone-local verbosity**

## 7.4 Demos

- Gate and Switch

## 8 CivAir

### 8.1 Summary

Drop-in to generate civilian air traffic. Runs out of the box, can be easily customized.

### 8.2 Dependencies

dcCommon, cfxZones

### 8.3 ME Integration

CivAir is customized via a config zone “**civAirConfig**” with the following attributes:

Name	Description
verbose	A value of “true” turns on debugging messages. Default is “false”
aircraftTypes	<p>A comma-separated list of Types (as defined in <a href="https://github.com/mrSkortch/DCS-miscScripts/tree/master/ObjectDB/Aircraft">https://github.com/mrSkortch/DCS-miscScripts/tree/master/ObjectDB/Aircraft</a> ) that define the aircrafts used for civilian flights. These must be fixed wing aircraft (i.e not helicopters).</p> <p>All airframe types are picked from this list, and each entry has the same chance to be picked. This means that if you list the same type twice, you increase the chance of that type to be picked.</p> <p>civAir defaults to the following list:</p> <ul style="list-style-type: none"><li>• Yak-40, Yak-40, C-130, C-17A, IL-76MD, An-30M, An-26B</li></ul> <p>Note that by default, the Yak-40 is twice as likely to be picked for a flight as an aircraft because its type is listed twice</p>
ups	Number of updates per second that civAir checks on its flights. By default, this is 0.05, or once every 20 seconds.
maxTraffic	Maximum number of civilian flights at the same time. Defaults to 10
maxIdle	<p>Number of seconds of an aircraft idling that can elapse before it is removed.</p> <p>CivAir determines that an aircraft is idling by checking if it is moving. If you set this number too low, a cold-starting aircraft may be removed before it can move.</p> <p>Defaults to 480 (seconds = 8 minutes)</p>
initialAirSpawns	Controls if at mission start half of maxTraffic immediately spawn in mid-air to start a mission with planes in the air.

You can add airfields to the inclusion / exclusion set with trigger zones as follows:

Name	Description
<b>civAir</b>	When present, the airfield closest to this trigger zone is added to either the inclusion or exclusion set. Additional keywords are supported:

Name	Description
	<ul style="list-style-type: none"> <li>• 'exclude' If the attribute's value is 'exclude' the closest airfield is added to the exclusion list. In all other cases, it is added to the inclusion list.</li> <li>• 'departure' or 'depart only' In this case, the airfield is added to the inclusion set only when looking for airfields to depart from</li> <li>• 'arrival' or 'arrive only' In this case, the airfield is added to the inclusion set only when looking for an airfield to land on.</li> </ul> <p>Note that you can add the same airfield multiple times by adding multiple trigger zones with a civAir attribute close to the same airfield. This will proportionally increase the likelihood of the airfield being picked for either destination or departure</p> <p>Note also that only functioning airfields are chosen. FARPS or ships are disregarded.</p> <p><b>MANDATORY</b></p>

## 8.4 Demos

- Virgin (Civ) Air
- Air Caucasus II
- One-Way Air

## 9 Clone Zone

### 9.1 Summary

Allows you to clone any groups, at any time, anywhere.

### 9.2 Dependencies

dcsCommon, cfxMX, cfxZones

### 9.3 ME Integration

Name	Description
cloner	Marks this ME Zone as a clone zone. <b>Value of this attribute is ignored</b> , use it to describe this cloner's function. <b>MANDATORY</b>
source	The source for the clone template, must be the name of a clone zone. When a clone cycle is initiated, the template is fetched from the source zone, and the units are then spawned around If this zone's center. If this attribute is present, this zone is not scanned for units to create a template from.  If you supply <b>more than one template zone names</b> , separated by comma (e.g., "SAM 9 small, SAM 9 big"), each time a clone cycle is initiated, the clone zone picks one template by random.  Defaults to <not present, zone scanned for units to create a template from>
turn	Degrees in which the clones are turned relative to the template's original position, relative to the zone's center. Defaults to 0 (zero)
moveRoute	If this attribute's value is true, all waypoints are move the same amount as the cloned units upon spawn. Only relevant if the zone is cloning another zone's template. When not present or false, all spawned units use the template's waypoints. Defaults to false
onStart	When set to false (default), the cloner will not spawn during start. Note that if this spawn zone is used to create a template, this results in an empty zone, as all units used for the template are destroyed during template creation.  Defaults to false ( <b>no spawn on start</b> of mission). <b>To spawn units at mission start, set this attribute to true.</b>
masterOwner	If not present, all cloned units retain the exact ownership of the units that the template was created from. If present, all cloned units are owned by the faction (red/blue/grey) that owns masterOwner. Note that using masterOwner, the coalition for the units that this cloner spawns can change during the mission.

Name	Description
	Defaults to <none, retain template ownership>
spawn? f? in? clone?	<b>DML Watchflag.</b> When triggered, the cloner starts a new clone cycle. Defaults to <none> You can use any synonym, but only one per zone
triggerMethod cloneTriggerMethod	Defines the trigger condition for the DML Watchflag. Defaults to "change"
preWipe	If this attribute is true, any remaining units from the previous cloning cycle are removed from the game when the next clone cycle starts. Use this to 'refresh' groups like SAMs or Tanks that can run out of ammo. Default: false
empty!	The value of this flag is changed according to method when all units from the last spawn have been destroyed, including all static objects.
method cloneMethod	Standard DML method for output flags. Defaults to "inc"
deSpawn? deClone? wipe?	Flag to watch for a change. If the value of this flag changes, the remaining units / static objects from the previous spawn are removed. Note that if you trigger deSpawn?, empty+1 will <b>not</b> trigger subsequently. Defaults to <none>
trackWith:	List of groupTracker zones. All spawned groups are added to these groupTrackers. If you have stacked the tracker on the same zone as the cloner, you can use a single asterisk '*' as zone name. Supports a comma-separated list of trackers if you simultaneously want to pass the cloned groups to multiple trackers, e.g. "GroundTrack, HeloTrack" This is useful if your cloner clones more than one group, and your trackers use filtering.
randomizedLoc rndLoc	Upon cloning, each cloned unit/object is displaced in a random direction by a random distance from 0 to the target zone's radius. Defaults to false
rndHeading	Upon cloning, each cloned unit/object assumes a random heading. Defaults to false
triggerMethod cloneTriggerMethod	Watchflag method for input flags. Defaults to 'change'
onRoad	Set to true to have any cloned unit deploy on the nearest road to the location it would spawn otherwise. This is very likely to change the template's formation, and can be a long way from the clone zone's intended spawn location, so use carefully. May also have other effects, such as bunching up the spawned units in unrealistically close proximity to each other. Defaults to false

**Supports DML flags**  
**Supports Watchflags**

## 9.4 Demos

- Attack of the CloneZ
- Once, twice, three times a maybe
- Clone Relations
- Frog Men Training
- Flag Fun
- Track This!
- Gate and Switch
- Reinforcements A La Carte
- Forever-looping Spawners
- Recon Mode - Reloaded

## 10 Count Down

### 10.1 Summary

A module that counts down flag signals (not time!) and can do various tricks with these signals.

### 10.2 Dependencies

dcsCommon, cfxZones

### 10.3 ME Integration

Name	Description
<b>countDown</b>	Marks this as a count down. The value of this attribute defines the number times until the count reaches zero This value supports ranges: if you specify a range (e.g., "3-5") each time the count down is initialized (at start, and when looping), a random number in the range (including upper and lower limit) is chosen. Defaults to 1 (one) <b>MANDATORY</b>
loop	If this attribute is true, a count down restarts after reaching zero. If the count down is given as a range, a new random start value is taken from that range (including upper and lower limit)
method ctdwnMethod	DML flag method for output. Use only one synonym per zone. Defaults to "flip"
count? in?	Watchflag. Triggering this flag constitutes a signal to count down by one. Use only one synonym per zone. Defaults to <none>
triggerMethod ctdwnTriggerMethod	Watchflag trigger conditions. Defaults to "change"
zero! out!	DML Output flag to bang when countdown reaches zero. Use only one synonym per zone. Defaults to <none>
tMinus!	DML Output flag to bang when the count value is lowered, and has not yet reached zero. Defaults to <none>
counterOut!	A flag, when given, is set to the current count value. The flag is updated each time that the counter is triggered via count?
disableCounter?	A Watchflag that when triggered, turns off the counter for good. Defaults to <none>

### 10.4 Demos

- Once, twice, three times a maybe
- The Zonal Countdown





## 11 CSAR Manager

### 11.1 Summary

CSAR Manager is a stand-alone module that adds CSAR (Combat Search And Rescue) operations to your missions. It consists of multiple ME parts, and in-game UI.

### 11.2 Dependencies

CSAR Manager requires dcsCommon, cfxZones, cfxPlayer, nameStats, cargoSuper

Optional: cfxCommander (when using CSAR Zones)

### 11.3 ME Integration

ME Integration consists of two parts: placing CSARBASES, which are zones in which a successful landing will complete the CSAR mission successfully (and return a lost pilot when using limited airframes), and placing CSAR Zones that essentially start CSAR Missions by placing downed pilots

Name	Description
<b>CSARBASE</b>	Must be present to identify this zone as CSAR Base where CSAR Missions can end. A helicopter must land inside this zone. Supports linked zones (for example if the BSAR Base is a ship). Each side that has CSAR Missions must have at least one such zone, or CSAR Missions can not be completed. There is no upper limit on the number of CSAR Bases a side can have. The value of this attribute can be used to name the CSAR Base, else the Zone's name is used. <b>MANDATORY</b>
coalition	The side that owns the CSAR Base. If neutral, both sides can use this as a base, else only the faction specified. Defaults to "neutral". Other possible values are "red" and "blue"
name	Optional name for CSARBASE.

Name	Description
<b>CSAR</b>	Identifies this as CSAR Zone that is converted into a CSAR mission upon mission start or when the startCSAR? flag is changed. <b>MANDATORY</b>
coalition	Faction (red/blue) for which this mission is generated
name csarName pilotName victimName	Name of this mission, recommended is to use a personal name, e.g. "Lt. Wesley Crasher"
freq	Frequency for the ELT (radio to home in on) in KHz. Random if not set
timeLimit	(currently not used)
weight	Weight of pilot (tbc)

deferred	If true, CSAR missions are only created when the startCSAR? flag changes. Default is false (a CSAR mission is automatically created when the main mission starts up)
in? startCSAR?	When the value of this flag changes, a new CSAR is created according to this Zone's attributes. Defaults to <none>

## 11.4 Demos

- CSAR of Georgia

## 12 Delay Flags

### 12.1 Summary

Change a flag on the output side a while after a change was detected on the input side

### 12.2 Dependencies

dcsCommon, cfxZones

### 12.3 ME Integration

Name	Description
timeDelay	Marks this as a delayFlag module. The value of this attribute defines the number of seconds to wait after activation before the output flag is set. Value can be a range in which case delayFlag picks a random number inside the range (including bounds). Defaults to 1 second <b>MANDATORY</b>
out! delayDone!	The flag to bang! after the delay has passed. Use only one synonym per Zone
method delayMethod	DML Flag method for output Defaults to "inc"
f? in? startDelay?	Watchflag for a change that starts the delay. Use any synonym, but only one per zone.
triggerMethod delayTriggerMethod	DML Method for Watchflags
stopDelay?	Stops a running delay. Has no effect on a stopped delay

**Supports DML flags**

**Supports Watchflags**

**Supports zone-local verbosity**

### 12.4 Demos

- Attack of the CloneZ
- Bottled Messages
- Clone Relations
- Flag Fun
- Track This!

## 13 Delicates

### 13.1 Summary

Makes units/objects/cargos brittle: they immediately explode when they receive some damage.

### 13.2 Dependencies

Delicates requires dcsCommon and cfxZones.

### 13.3 ME Integration

Name	Description
<b>delicates</b>	Marks all static objects and units that are inside this zone when the mission starts up as 'delicate'. If they get damaged at all, they immediately explode. Note that if these units move later outside this zone, they remain delicates, while units that move inside this zone later do NOT become delicates.  Value of this attribute is ignored  <b>MANDATORY</b>
power	Strength of the explosion when the delicate object is triggered. Defaults to 10
f! out! delicatesHit!	Flag to bang! when one of the units/objects defined by this zone explodes. Defaults to <none>
method delicatesMethod	DML Method for output flags Defaults to 'inc'
remove	When set to true, the delicate object/unit is removed from the game when it explodes. Defaults to true
triggerMethod delicateTriggerMethod	Watchflag method for all inputs
blowAll?	Sending a signal on this input causes all surviving delicates defined by this zone to blow up. When you feed back the delicatesHit! Signal into this input, one hit kills all.
safetyMargin	A number that defines how much damage the object can sustain (relative to its initial life) before it explodes. Expressed as a fraction from 0 (0%) to 1 (100%). For example, 0.1 means that the object can sustain 10% damage before it explodes. Defaults to 0 (any damage makes it blow up)

**Supports DML Flags**

**Supports Watchflags**

**Supports zone-local verbosity**

## **13.4 Demos**

- Delicate Subjects

## 14 FARP Zones

### 14.1 Summary

A zone linked to a FARP (and thus conquerable) that automatically provides service vehicles.

### 14.2 Dependencies

dcsCommon, cfxZones

### 14.3 ME Integration

Name	Description
<b>FARP</b>	Indicates that this zone is a FARP zone. Value is ignored. <b>MANDATORY</b>
rPhiHDef	Radius (in m), Phi (degrees) and Heading (degrees) of the center point around which the <b>defenders</b> deploy. Defaults to 0, 0, 0
rPhiHRes	Radius (in m), Phi (degrees) and Heading (degrees) of the center point around which the <b>resource</b> vehicles deploy as a line. Defaults to 0, 0, 0
redDefenders	typeStrings of defender vehicles. Example "ZSU-23-4 Shilka, ZSU-23-4 Shilka". Defaults to "none" Special encoding: "none" – no vehicles
blueDefenders	typeStrings of defender vehicles. Example "Roland ADS, Roland Radar, Roland ADS". Defaults to "none" Special encoding: "none" – no vehicles
formation	Formation of the defenders group. See dcsCommon for supported group formations. Defaults to 'circle_out'.
rFormation	Radius of the circle that the defenders assemble in. Defaults to 100m
hidden	Set to "no" if FARP is visible on the F10 map (and colored according to owner). Defaults to "no"
hideRed hideBlue hideGrey	For any of these three attributes, the FARP is hidden if it belongs to that faction. For example, if hideRed is set to true, the FARP is shown on the map while it belongs to neutral or blue, but disappears when it is owned by red.

### 14.4 Demos

- FARP and away

## 15 Group Tracker

### 15.1 Summary

A module that counts the groups in a set, and changes flags when the number changes. Extremely versatile count based on the tracked groups' survival.

### 15.2 Dependencies

dcsCommon, cfxZones

### 15.3 ME Integration

To add all groups that have at least one unit inside the zone to a groupTracker, add the following attribute to the zone:

Name	Description
addToTracker:	<p>List of groupTracker zones. All groups that have at least one unit inside this zone are added to these groupTrackers. This happens only at mission start-up, and therefore only work for non-player-controlled planes (since player-controlled planes do not exist at mission start-up). If your player group contains AI planes, place one of those into the zone, and that group can be added to a tracker.</p> <p>If you have stacked the tracker on the same zone, you can use a single asterisk "*" as zone name.</p> <p>Supports a comma-separated list of trackers if you simultaneously want to pass the groups to multiple trackers, e.g. "GroundTrack, HeloTrack"</p> <p>This is useful if the zone contains more than one group, and your trackers use filtering</p> <p>Add all groups that have at least one unit in this zone to the tracker whose zone name is given in the Value field.</p>

To add a groupTracker to a zone

Name	Description
tracker	<p>Marks this zone as a groupTracker. It can be referenced by the zone's name passed in the trackWith: and addToTracker: attributes. When referenced locally, a single asterisk "*" can be used as wildcard name for easy copy/paste of the entire stack</p> <p><b>MANDATORY</b></p>
addGroup!	<p>Whenever a group is added to the tracker, the value of this flag is increased. If not changed by other modules, this flag also doubles as a running total of all groups added to the tracker</p> <p>Defaults to &lt;none&gt;</p>
removeGroup!	<p>Whenever a tracked group is destroyed, the value of this flag is increased. If not changed by other modules, this flag also doubles as a running total of all watched groups that have been destroyed while they were tracked</p>

Name	Description
	Defaults to <none>
numGroups!	The value of this flag always represents the number of groups currently watched by this tracker. <b>This value is updated 1/ups times per second.</b> Defaults to <none>
groupFilter	Which unit categories to track. If no attribute is given, <b>all</b> categories are tracked. When you supply a groupFilter attribute, <b>only that category is accepted</b> when attempting to add to a tracker. Currently supported are <ul style="list-style-type: none"> <li>• 0 (zero) or "aircraft" or "air"</li> <li>• 1 or "helo" or "heli" or "helicopter"</li> <li>• 2 or "ground"</li> <li>• 3 or "ship"</li> <li>• 4 or "train"</li> </ul> Defaults to no filtering

## 15.4 Demos

- Track This!
- Moving Spawners II
- Impossible Impostors



## 16 Guardian Angel

### 16.1 Summary

Provides out-of-the-box protection for aircraft against guided missiles.

### 16.2 Dependencies

Guardian Angel requires dcsCommon and cfxZones

### 16.3 ME Integration

Guardian Angel uses a config zone “guardianAngelConfig” to control all settings

Name	Description
verbose	A value of “true” turns on debugging messages. Default is “false”
autoAddPlayer	When set to true, player planes are automatically added to Guardian Angel's watchlist. Default is true
launchWarning	If true, Guardian Angel announces a missile launch. Default is true
intervention	If true, Guardian Angel destroys a missile before it destroys a watched aircraft. Default is true
announcer	If set to false, Guardian Angel suppresses all announcements. Defaults to true
private	If set to true, all announcements are only made to the group that a missile was fired at. Set to false (everyone can see)
explosion	<p>Guardian Angel can add a mostly harmless explosion when a missile is removed due to an intervention. If this value is smaller than one (e.g., -1) this feature is turned off. If you enter a value &gt; 0 (zero), an explosion with a magnitude of this value is placed in direction of that missile's last location, 500m from the aircraft. A mostly harmless value is 1.0 (one point zero)</p> <p><b>WARNING I</b> Even though this explosion is usually harmless for the protected plane, it can pose lethal to any other plane (wingmen).</p> <p><b>WARNING II</b> The explosive effect is only harmless to the protected plane if the explosion value is small (e.g., 1). If you enter sufficiently larger values, the shock wave can destroy even the protected plane.</p> <p>If you set this value to see explosions, make the value 1.0</p> <p>Defaults to -1 (off)</p>
fxDistance	When using explosions, this is the distance (in meters) away from the aircraft where the (real) explosion is going to take place.

Name	Description
	Defaults to 500
active	The state that Guardian Angel starts up in. True means that it is active, false that it is turned off. Defaults to 'false'
activate? on?	Watchflag to turn on (activate) guardian angel. Defaults to <none>
deactivate? off?	Watchflag to turn off (deactivate) guardian angel. Defaults to <none>

You can selectively add and remove aircraft from protection by Guardian Angel by placing them in a zone with the “guardian” attribute:

Name	Description
guardian	<b>MANDATORY</b>  Tells Guardian Angel how to treat aircraft inside the trigger zone: <ul style="list-style-type: none"> <li><i>true</i> All aircraft inside this zone are protected by Guardian Angel</li> <li><i>false</i> All aircraft inside this zone will not receive protection from Guardian Angel.</li> </ul> Defaults to 'true' (all aircraft inside are protected)

## 16.4 Demos

- Missile Evasion (Guardian Angel)
- Guardian Angel Reloaded

## **17 Helo Troops**

### **17.1 Summary**

This module provides instant out-of-the box ability for troop transport helicopters to pick up and deploy infantry

### **17.2 Dependencies**

Tbc

### **17.3 ME Integration**

Tbc

### **17.4 Demos**

- Helo Trooper

## 18 Impostors

### 18.1 Summary

Impostors allow you to switch AI-controlled units to their static object equivalents (“impostor”). Impostors will not react to enemies, and consume less CPU. You can use flags to control if a group is in impostor or controlled state.

### 18.2 Dependencies

Impostors require dcsCommon, cfxMX and cfxZones.

### 18.3 ME Integration

Name	Description
<b>impostor?</b>	Marks all groups that have at least one unit inside this zone as potential impostor, giving them the ability to change between static object and AI-controlled unit. The value of this attribute is a Watchflag that triggers transition of all surviving units from AI-controlled to static object.  <b>MANDATORY</b>
reanimate?	Watchflag that triggers transition of all surviving static units to AI-controlled units. They immediately restart any waypoint actions or route orders (if given). Ground units will start moving their first (not initial) waypoint.
triggerMethod impostorTriggerMethod	Method that triggers inputs (DML Watchflags) Defaults to “change”
onStart	If the value of this attribute is true, all units are turned into impostors at the start of the mission. Default is false
blink	The value of this attribute specifies the brief interval (in seconds) between removing the impostor and spawning of the AI-controlled units. Only required for AI aircraft. A good value is 0.1 – 0.2; a value of zero or negative value means no blinking. Defaults to -1 (no blink interval)
trackWith:	Name of a zone with a groupTracker attached. All units are added to that tracker when they are AI-controlled, and removed when they are turned into impostors. Reanimating them subsequently will again add them to the tracker etc.
allDead!	DML flag to bang! when all groups that are managed by this impostor zone have been destroyed
method impostorMethod	DML method for output Defaults to “inc”

**Supports DML Flags**

**Supports Watchflags**

**Supports zone-local verbosity**

## **18.4 Demos**

- Impossible Impostors

## 19 Limited Airframes

### 19.1 Summary

Set a maximum per side on the number of player pilots that can be lost.

### 19.2 Dependencies

dcsCommon, cfxZones, cfxPlayer

### 19.3 ME Integration

Most features of Limited Airframes are controlled via config zones:

Name	Description
verbose	A value of “true” turns on debugging messages. Default is “false”
enabled	Controls whether or not Limited Airframes is in effect. Defaults to “true”
userCanToggle	Controls whether players can turn Limited Airframes on and off during the mission. Defaults to “true”
maxRed	Maximum (and starting) number of pilots for the red coalition. Set to -1 to make the number unlimited. Defaults to -1 (unlimited)
maxBlue	Maximum (and starting) number of pilots for the blue coalition. Set to -1 to make the number unlimited. Defaults to -1 (unlimited)
#red	Flag that continuously is set to the current number of pilots remaining for Red
#blue	Flag that continuously is set to the current number of pilots remaining for blue
redWins! redWinsFlag!	Flag to bang! when blue has lost all pilots and red wins. Defaults to <none>
blueWins! blueWinsFlag!	Flag to bang! when red has lost all pilots and blue wins. Defaults to <none>
method	DML bang! method. Defaults to ‘inc’
warningSound	Name of sound file to play when limited airframes is displaying a message. Defaults to <none>
winSound	Name of sound file to play for winning side when other side has lost all pilots. Defaults to <none>
loseSound	Name of sound file to play for the side that has lost all pilots and therefore lost the engagement. Defaults to <none>

On the map, you should place safe zones (one per side that has limits on player pilots) using the following attributes

Name	Description
pilotsafe	Marks this zone as safe for pilots to change into other airframes when landed. <ul style="list-style-type: none"><li>• If the value to this attribute contains neither the word ‘red’ nor ‘blue’, it is safe for all coalitions</li><li>• If the value of this attribute contains the word ‘red’ this zone is safe for the red coalition</li></ul>

Name	Description
	<ul style="list-style-type: none"> <li>• If the value of this attribute contains the word 'blue' this zone is safe for the blue coalition</li> </ul> <p>Note that safe state may be contingent on ownership of the zone.</p> <p><b>MANDATORY</b></p>

## 19.4 Demos

- Pilots at their limit

## 20 Map Markers

### 20.1 Summary

Allows you to place markers on the F10 map.

### 20.2 Dependencies

dcsCommon, cfxZones

### 20.3 ME Integration

Name	Description
<b>mapMarker</b>	Turns on the map marking feature. Simply must be present. Content of this property is displayed as text on the Map. Example "Destroy all vehicles in this area" <b>MANDATORY</b>
coalition	Side that sees this marker. Can be "red", "blue", "neutral", or "all". You can also substitute "1" for red, and "2" for blue. Defaults to "all"

### 20.4 Demos



## 21 Messenger

### 21.1 Summary

A module that generates a text and/or audio output.

### 21.2 Dependencies

dcsCommon, cfxZones

### 21.3 ME Integration

Name	Description
messenger?	Watchflag. When triggered, the module will display the message and/or play sound. Anchors messenger to this zone  <b>MANDATORY</b>
triggerMethod msgTriggerMethod	Defines the trigger condition for DML Watchflags. Use only one synonym per zone Defaults to "change"
message	The text of the message to be displayed  <b>TEXT WILDCARDS</b> <ul style="list-style-type: none"><li>• &lt;n&gt; creates a new line</li><li>• &lt;z&gt; is replaced with zone's name</li><li>• &lt;t&gt; is current time in HH:MM:SS format</li><li>• &lt;lat&gt; the latitude of the zone's current position</li><li>• &lt;lon&gt; the longitude of the zone's current position</li><li>• &lt;mgrs&gt; the zone's current position in MGRS coordinates</li><li>• &lt;v&gt; is replaced with the value currently held by the flag specified in <i>messageValue</i>?</li></ul>
messageValue?	A flag name that is read whenever a message is put out. The value that this flag contains can be accessed with the *value wildcard in the message attribute
clearScreen	If true, erase all existing messages. Defaults to false
soundFile	Name of the sound file (including extension like '.wav') that is to be played. Defaults to '<none>'. Note that the sound file's name must be specified relative to the mission's default location for sound files (I10n/DEFAULT/). If you use ME to import the sound files, you do not have to specify the location. Remember to import the sound file into the mission else no sound will play.
coalition msgCoalition	The coalition that the message/sound is played to. If no coalition is given, text and sound are played to all. Legal values are "red", "blue", "neutral", 0, 1, 2 Default is <none> (play to all).
messageOn?	When the value of this flag changes, the messenger is turned on. If it already was on, nothing happens All messengers start in 'On' state and require at least one signal on messageOff to disable it.

	Defaults to <none>
messageOff?	When the value of this flag changes, the messenger is turned off. Any further messages are suppressed. If the messenger already was turned off, nothing happens. Defaults to <none>

**Supports DML Flags**  
**Supports DML Watchflags**

## 21.4 Demos

- Bottled Messages
- Frog Men Training
- The Zonal Countdown
- Follow Me!
- CSAR of Georgia
- Track This!
- Watchflag Demo
- Radio Go-Go
- xFlags Field Day
- Count Base's Blues
- Gate and Switch
- Moving Spawners II
- Reinforcements A La Carte

## 22 NDB

### 22.1 Summary

Allows you to place an NDB in any zone. This includes linked zones so you can place NDBs that follow ships.

### 22.2 Dependencies

dcsCommon, cfxZones.

### 22.3 ME Integration

Name	Description
NDB	<p>Creates an NDB at the zone's center. If the zone is linked to a unit, this NDB will automatically update to the unit's location.</p> <p><b>The value of this attribute is the frequency (in MHz) at which the NDB transmits (e.g. 121.5 for 121.5 MHz, 0.42 for 420 kHz)</b></p> <p><b>MANDATORY</b></p>
fm	<p>If true, the transmission is in FM, else in AM</p> <p>Defaults to false (AM)</p>
ndbSound	<p>Name of the sound file with extension that is to be transmitted. Defaults to '&lt;none&gt;'. Note that the sound file's name must be specified relative to the missions default location for sound files (I10n/DEFAULT/). If you use ME to import the sound files, you do not have to specify the location.</p> <p>Remember to import the sound file into the mission else no sound will play.</p>
watts	<p>Transmission power (in watts) for the NDB. 100 Watts usually has a range of some 150 km.</p> <p>Defaults to 100 Watts</p>
paused	<p>If set to true, on mission start the NDB will not start up. Use the "on?" watch flag attribute or API to turn it on.</p> <p>Defaults to false</p>
on?	<p>Watchflag. <b>Each time the flag triggers, the NDB is started (will also cause the transmission sound to rewind).</b> The current paused value is ignored, and then set to false after the NDB has started.</p> <p>Defaults to no flag to watch</p>
off?	<p>Watcheflag. <b>Each time the flag triggers, the NDB is stopped.</b> paused value is set to true after the NDB has stopped.</p> <p>Defaults to no flag to watch</p>
triggerMethod ndbTriggerMethod	<p>Defines the trigger condition for DML Watchflags. Use only one synonym per zone</p> <p>Defaults to "change"</p>

## **22.4 Demos**

- ADF and NDB Fun

## 23 Object Destruct Detector

### 23.1 Summary

Generates a signal (flag change) when the map object that is referenced by the zone is destroyed.

### 23.2 Dependencies

dcsCommon, cfxZones

### 23.3 ME Integration

Name	Description
<b>OBJECT ID</b>	THIS ATTRIBUTE IS FILLED BY ME AND MUST NOT BE CHANGED <b>MANDATORY</b>
<b>NAME</b>	THIS ATTRIBUTE IS FILLED BY ME AND MUST NOT BE CHANGED <b>MANDATORY</b>
method oddMethod	DML Method for output flags. Defaults to "inc"
f! destroyed! objectDestroyed!	The flag to bang! when the object is destroyed. Use only one synonym per zone. Defaults to "*none"

### 23.4 Demos

- Object Destruct Detection

## 24 Object Spawn Zones

### 24.1 Summary

Allows static objects and cargo to spawn according to an attribute (type)

### 24.2 Dependencies

dcsCommon, cfxZones, (cfxCargoManager)

### 24.3 ME Integration

Name	Description
objectSpawner	Marks this ME Zone as a spawn zone. <b>Value of this attribute is ignored</b> , use it to describe what it spawns to make mission editor easier for you <b>MANDATORY</b>
f? spawn? spawnObjects?	An ME-compatible flag (e.g. 100) that this object spawner monitors for change. Whenever the value of the monitored flag changes, a new set of objects is spawned immediately, ignoring all maxSpawn and cooldown rules.
pause?	Flag to observe. Each time the flag's value changes, the spawner's 'paused' setting is forced to 'true'. Used to 'pause' a spawner
activate?	Flag to observe. Each time the flag's value changes, the spawner's 'paused' setting is forced to 'false'. Used to 'activate' a paused spawner
types	Type string array for the STATIC OBJECTS that are spawned. Example "White_Tyre, Red_Flag". These objects may look like units (if you use the type string for a ground unit or aircraft), but they are static.  <b>WARNING:</b> Blanks are part of the type, and blanks directly before and after the last character are automatically stripped. All static objects given here are stacked on top of each other, and count as one instance (the example creates a tire with a red flag in the middle) <b>MANDATORY</b>
count	The number of times that the combined object in types is to be repeated. If count equals one (or is omitted), the objects defined in types are assembled in the center of the zone. Otherwise, the objects are distributed over the zone's circumference count times. Defaults to one
country	The country for which the static objects are spawned. Examples: 0 = Russia, 1 = Ukraine, 2 = USA etc. Defaults to 2 (USA)
baseName	Used to create the names that uniquely identify the objects that are spawned to DCS. <b>If provided, MUST BE UNIQUE</b> for each spawner. If you do not provide a baseName, a unique name is generated for you.
cooldown	Number of seconds after the last spawn was removed before new objects are spawned. Default is 60 seconds
autoRemove	Wait for the spawned objects to be removed or destroyed, immediately start cooldown, then re-spawn according to rules. Default is false

Name	Description
autoLink	Only used when the spawner is linked to a unit: should the spawned objects move with the unit that the zone is linked to (usually ships, but can also be other objects). Defaults to true. Set to false if the spawner should 'drop' the objects to the ground.
heading	Orientation of the objects when they are spawned. Default is 0 (North)
weight	Used with cargo objects: the weight of this object in kg. Defaults to zero.
isCargo	Are these objects to be picked up by helicopters? Defaults to false.
managed	Used only if the objects spawned are cargo. If true, cargo objects are automatically registered with cfxCargoManager when they are spawned and cfxCargoManager is loaded). Defaults to true
maxSpawns	Number of times that the spawner spawns the objects. Defaults to 1 (one)
paused	A paused spawner will not spawn automatically (but can be forced to spawn via API or query flag f?). Set to true to pause spawning. Defaults to false.
requestable	This spawner should only spawn on request (i.e. via API or from other zones). Forces paused to true. Default value is false
useDelicates	Name of Delictates Zone that is used to assign delicate status when this spawner spawns objects

## 24.4 Demos

- ME Triggered Spawns
- Spawn Zones (training and lasing)
- Random Glory
- Helo Cargo

## 25 Owned Zone

### 25.1 Summary

Zones that can be conquered and generate a signal when conquered

### 25.2 Dependencies

dcsCommon, cfxZones, (cfxGroundTroops)

### 25.3 ME Integration

Name	Description
owner	Coalition that owns the zone at beginning of Mission. Can be 0, 1, 2 or "red", "blue", "neutral". If nothing or some illegal value give, this defaults to neutral (0) <b>MANDATORY</b>
conq+1	<del>Increase this flag's value by 1 (one) each time it is conquered.</del> Defaults to <none>
conquered!	Flag to bang! when this zone changes hands Defaults to <none>
defendersRED	A string, coma separated, that specifies the types of troops to spawn when the zone is owned by RED. Example: "Soldier M4,Soldier M4" places two Infantry soldiers. <b>Warning:</b> these types need to <i>exactly</i> match DCS's types. Be sure not to accidentally insert blanks. Special types: "none" – no troops Defaults to "none"
defendersBLUE	A string, coma separated, that specifies the types of troops to spawn when the zone is owned by RED. Example: "Soldier M4,Soldier M4" places two Infantry soldiers. <b>Warning:</b> these types need to <i>exactly</i> match DCS's types. Be sure not to accidentally insert blanks. Special types: "none" – no troops Defaults to "none"
attackersRED	A string, coma separated, that specifies the types of troops to spawn when the zone is owned by RED. Example: "Soldier M4,Soldier M4" places two Infantry soldiers. <b>Warning:</b> these types need to <i>exactly</i> match DCS's types. Be sure not to accidentally insert blanks. Special types: "none" – no troops Defaults to "none"
attackersBLUE	A string, coma separated, that specifies the types of troops to spawn when the zone is owned by RED. Example: "Soldier M4,Soldier M4" places two Infantry soldiers. <b>Warning:</b> these types need to <i>exactly</i> match DCS's types. Be sure not to accidentally insert blanks. Special types: "none" – no troops Defaults to "none"
formation	Formation of the defenders group. See dcsCommon for supported group formations. Defaults to 'circle_out'.
attackFormation	Formation of the attackers group. See dcsCommon for supported group formations. Defaults to 'circle_out'.



Name	Description
spawnRadius	Radius of circle that the defenders are placed on. Defaults to slightly less than zone radius, so defenders are always inside the zone they are defending. Defaults to 0.
attackRadius	Radius of circle in which the attackers spawn after they are produced. Defaults to zone radius
attackDelta	Distance from center of zone in which attackers spawn circle is located. Defaults to 10.
attackPhi	Angle (direction) in degrees from zone center where attackers are spawning. Defaults to 0.
paused	Pauses zone. "true" or "yes" means that the zone is paused. A paused zone produces no attackers nor defenders, but will detect capture normally. Capturing a paused zone will currently not unpause the zone. Do that in the capture callback. Defaults to "no"
unbeatable	"true" or "yes" makes it unbeatable. Zone can't be conquered by other side. Defaults to "no"
untargetable	"true" or "yes" makes it untargetable. Zone will not be targeted by troops with 'attackOwnedZones'. Defaults to "no"
hidden	"true" or "yes" hides it. Zone is not shown on F10 Map. Defaults to "no"

## 25.4 Demos

- Owned Zones ME Integration

## 26 Persistence

### 26.1 Summary

This module provides persistence (load and save) functionality to modules. Must load before any mode that is to use persistence. Requires that the DCS instance that is running the mission be de-sanitized for lfs and io.

### 26.2 Dependencies

Persistence requires dcsCommon and cfxZones.

### 26.3 ME Integration

You configure the persistence module with a Trigger Zone named 'persistenceConfig'

Name	Description
verbose	A value of "true" turns on debugging messages. Default is "false"
versionID	If present, this turns on version matching. When a mission starts up, persistence checks the value provided via the Zone with the one saved. If they do not match, the entire save data is discarded, and the mission starts fresh Defaults to <none>
serverDir	Path from the DCS standard directory (usually "C:\user\name\saved games\DCS.openbeta\" or "C:\user\name\saved games\DCS\" to the missions directory. Use this if you set up your DCS different (usually important for dedicated servers). Defaults to "Missions\"
saveDir	Name for the mission's data directory. Defaults to "<mission name> (data)". This directory is created in the serverDir automatically if it does not exist If you set saveDir to "", the mission saves it's data directly into serverDir Defaults to "<mission name> (data)" if a configuration zone is present, none without configuration zone
saveFileName	Name for the file that persistence uses to write mission data. Defaults to "<mission name> Data.txt"
saveInterval	Controls auto-save. Any value larger than zero will turn on auto save. The value you give here is the number of minutes between auto saves. Auto-saves co-operate with manual saves, so you can use both methods in your mission Defaults to -1 (auto-save off)
cleanRestart?	DML Watchflag. A change signal on this input triggers a "fresh start" request: next time the mission starts up, it won't load mission data. Defaults to <none>
saveMission?	DML Watchflag. A change signal on this input triggers a 'manual' save. Defaults to <none>

You can use Trigger Zones with the 'saveFlags' attribute to list the flags that persistence should save.

Name	Description
<b>saveFlags</b>	A list of flags that you want to be saved with the mission. Supports local flags (e.g., “*go”) and numbered ranges (e.g. “3-17”). <b>MANDATORY</b>

## 26.4 Demos

- Being persistent

## **27 Player Score**

### **27.1 Summary**

A module to keep award and tabulate kill score for players

### **27.2 Dependencies**

Tbc

### **27.3 ME Integration**

Tbc

### **27.4 Demos**

- Keeping The score
- More Score

## 28 Pulse Flags

### 28.1 Summary

Flag “Heartbeat” – (somewhat) regularly sets/changes a flag

### 28.2 Dependencies

dcsCommon, cfxZones

### 28.3 ME Integration

Name	Description
<b>pulse!</b>	Marks this as a pulser. The value describes the flags to change on each pulse. The flags are changed according to the method attribute <b>MANDATORY</b>
method pulseMethod outputMethod	DML Flag output method Defaults to “flip”
done! pulsesDone!	This flag’s value is changed when the pulser completes a fully run of pulses. Can only happen when the <i>pulses</i> attribute supplies a positive number. Use only one synonym per zone. Defaults to <none>
triggerMethod pulseTriggerMethod	Watchflag condition for input flags. Use only one synonym per zone
activate? startPulse?	Watchflag. When triggered, a paused pulser is reset and then restarted. Use only one synonym per zone. Defaults to <none>
pause? pausePulse?	Watchflag. When triggered, a pulser is paused. Use only one synonym per zone. Defaults to <none>
<del>paused pulseStopped</del>	<del>When true, the pulser does not start at the beginning of a mission but waits for a trigger on activate?-flag. Defaults to false</del>
onStart	When set to false, a pulser starts paused, else active.  <b>Defaults to true</b> (pulser starts automatically)
pulses	The number of pulses to complete. <ul style="list-style-type: none"><li>• If set to -1, the pulser runs until the mission ends or the pause?-flag changes</li><li>• If set to a number, the pulser will generate that many pulses.</li><li>• If set to a range (e.g. “3-5”) the pulser will generate a random number of pulses within that range.</li></ul> Defaults to -1 (endless)

Name	Description
time pulseInterval	Seconds between pulses. You can supply a range (two numbers separated by a hyphen, e.g. "4-19"), the time between pulses is randomized after each pulse to a number in that range. Defaults to 1
zeroPulse	Usually, a pulser starts with an initial pulse ("pulse zero"). This initial pulse can be delayed by <i>time</i> by setting zeroPulse to false. The effect is that the initial pulse happens after the first delay. Default is true (initial pulse immediately)

**Supports DML Flags**

**Support Watchflags**

**Supports zone-local verbosity**

## 28.4 Demos

- Pulsing Fun
- Frog Men Training
- The Zonal Countdown
- Watchflag Demo
- Forever-looping Spawners

## 29 Radio Menu

### 29.1 Summary

Adds a configurable player menu to the Communications→F10 Other menu, with up to four menu items (commands). Supports cooldown.

### 29.2 Dependencies

Radio Menu requires dcsCommon and cfxZones.

### 29.3 ME Integration

Name	Description
<b>radioMenu</b>	Name of the menu to install in the Communications→F10 Other menu.  <b>MANDATORY</b>
coalition	Optional coalition that gains access to this menu. If omitted, all coalition have access. 'blue' or 'red' restrict access to that coalition.
itemA	Name of itemA in this menu. If this attribute is omitted, no menu item appears
itemB	Name of itemB in this menu. If this attribute is omitted, no menu item appears
itemC	Name of itemC in this menu. If this attribute is omitted, no menu item appears
itemD	Name of itemD in this menu. If this attribute is omitted, no menu item appears
A!	DML flag to bang when itemA is chosen. Defaults to <none>
B!	DML flag to bang when itemB is chosen. Defaults to <none>
C!	DML flag to bang when itemC is chosen. Defaults to <none>
D!	DML flag to bang when itemD is chosen. Defaults to <none>
cooldownA	Cooldown (in seconds) after itemA is chosen before it becomes available again. Defaults to 0 (immediately available again)
cooldownB	Cooldown (in seconds) after itemA is chosen before it becomes available again. Defaults to 0 (immediately available again)
cooldownC	Cooldown (in seconds) after itemA is chosen before it becomes available again. Defaults to 0 (immediately available again)
cooldownD	Cooldown (in seconds) after itemA is chosen before it becomes available again. Defaults to 0 (immediately available again)
busyA	Message to display when itemA is chosen while cooldown is still active. Defaults to "Please stand by (<s> seconds)". Supports Time Wildcards <s>, <m>, <h>, <:s>, <:m> and <:h>
busyB	Message to display when itemB is chosen while cooldown is still active. Defaults to "Please stand by (<s> seconds)". Supports Time Wildcards <s>, <m>, <h>, <:s>, <:m> and <:h>

Name	Description
busyC	Message to display when itemC is chosen while cooldown is still active. Defaults to "Please stand by (<s> seconds)". Supports Time Wildcards <s>, <m>, <h>, <:s>, <:m> and <:h>
busyD	Message to display when itemD is chosen while cooldown is still active. Defaults to "Please stand by (<s> seconds)". Supports Time Wildcards <s>, <m>, <h>, <:s>, <:m> and <:h>
method radioMethod	DML method to bang flags. Defaults to 'inc', meaning that each time that a menu item is chosen, the flag's number is increased, generating a signal. To emulate ME's native menu method that sets a flag to a value <v>, use that number <v> as method
radioTriggerMethod	Watchflag method for inputs Defaults to "change"
removeMenu?	Watchflag that triggers removal of entire menu
addMenu?	Watchflag that triggers adding the menu if it wasn't shown or removed previously
menuVisible	When set (as per default) the menu is shown at the start of the mission. When set to false, the mission starts up with the menu hidden and requires a signal on addMenu? to appear Default to true (menu is visible on mission start)

### Supports DML Flags

### Supports Watchflags

### Supports zone-local verbose

Use the following wildcards (note that they are identical to messenger's 'display as time wildcards) in busyX:

- <s>  
remaining cooldown in seconds. E.g., if remaining cooldown is 254, <s> is replaced with '254'
- <m>  
remaining cooldown as whole minutes. E.g., if remaining cooldown is 254, <m> is replaced with '4', while 3891 returns "64"
- <h>  
remaining cooldown as whole hours. E.g., if remaining cooldown is 3891, <m> is replaced with '1'
- <:s>  
remaining cooldown converted to a seconds time value (0-60) and formatted with leading zero. E.g., if remaining cooldown is 64, <:s> is replaced with '04'
- <:m>  
remaining cooldown converted to a minutes time value (0-60) and formatted with leading zero. E.g., remaining cooldown is 64, <:m> is replaced with '01', and 803 returns "13"



- <:h>  
remaining cooldown converted to an hours time value and formatted with leading zero. E.g., if remaining cooldown is 3764, <:h> is replaced with '01'

## **29.4 Demos**

- Reinforcements A La Carte
- Recon Mode reloaded
- Guardian Angel reloaded

## 30 Radio Trigger

### 30.1 Summary

Provides an interface for ME-based Communication→Other Radio Items, allowing multiple uses by re-setting the flag after it has been triggered.

### 30.2 Dependencies

dcsCommon, cfxZones

### 30.3 ME Integration

Name	Description
radio?	Watchflag. Triggers a radio cycle, then resets this flag to its pervious value  <b>MANDATORY</b>
triggerMethod radioTriggerMethod	Method that triggers the Watchflag Defaults to 'change'
method rtMethod	Method how the output flag should be triggered. Defaults to 'inc'
out! rtOut!	DML Flag to set when the module triggers Defaults to <none>

**Supports DML Flags**

**Supports Watchflags**

**Supports zone-local verbose**

### 30.4 Demos

- Radio go go

## 31 Raise Flag

### 31.1 Summary

A simple, DML way to set flags to values. Supports randomization and delayed setting of flags.

### 31.2 Dependencies

dcsCommon, cfxZones

### 31.3 ME Integration

Name	Description
<b>raiseFlag</b> <b>raiseFlag!</b>	Marks this as a flag raiser. The value of this attribute is the flag that is to be raised. Use only one synonym per zone <b>MANDATORY</b>
value	Method or value to set the flag to. Supports <ul style="list-style-type: none"><li>• 'inc' increment the flag's current value by one</li><li>• 'dec' decrements the flag's current value by one</li><li>• 'flip' sets the flag's current value to 0 if it was anything but zero, and to 1 if it was zero.</li><li>• (number) – set the flag to this number</li></ul> Default is 'inc'
afterTime	Amount of time (in seconds) after mission start to set the flag. Can be a range. If a range is given, the time is a random number from this range. <b>If this attribute is omitted, the flag is set 0.5 seconds after the mission starts.</b>
stopFlag?	Only useful in conjunction with afterTime. A Watchflag. When triggered and raiseFlag is still waiting for afterTime, raiseFlag is 'disarmed' and raising the flag is cancelled. It will not be raised later. Once stopped, it cannot be re-started.
triggerMethod raiseTriggerMethod	Watchflag condition for stopFlag?

**Supports DML Flags**

**Supports Watchflags**

### 31.4 Demos

- Flag Fun
- Attack of the CloneZ



## 32 Recon Mode

### 32.1 Summary

Provides out-of-the-box advanced recon abilities for aircraft.

### 32.2 Dependencies

Tbc

### 32.3 ME Integration

Zone to make aircraft scouts or remove scout abilities:

Name	Description
scout	Marks all aircraft (fixed- and rotor-wing) inside the zone. If the attribute's value is 'true', the aircraft have recon ability. If the value is false, they are 'blind', i.e. they have no recon abilities. Defaults to 'true' <b>MANDATORY</b>
dynamic	Controls if all units that start with the same name are automatically included. This is helpful for clone zones that base all names for clones on the name of the unit in the template. Defaults to false

Zone to mark priority and blacklisted ground forces:

Name	Description
recon	Marks all ground groups inside this zone as recon relevant. If the value is "black" all groups that have at least one inside this zone are added to the blacklist, otherwise they are added to the priority target list Defaults to "prio" <b>MANDATORY</b>
dynamic	Controls if all groups that start with the same name are automatically included. This is helpful for clone zones that base all names for clones on the name of the unit in the template. Defaults to true
prioMessage	A message that is displayed to the coalition that the scout belongs to. Can contain most of the text wildcards that the messenger module provides: <ul style="list-style-type: none"><li>• &lt;n&gt; creates a new line</li><li>• &lt;z&gt; is replaced with zone's name</li><li>• &lt;t&gt; is current time in HH:MM:SS format</li><li>• &lt;lat&gt; the latitude of the zone's current position</li><li>• &lt;lon&gt; the longitude of the zone's current position</li><li>• &lt;mgrs&gt; the zone's current position in MGRS coordinates</li></ul> <i>Only applicable for priority targets</i> (i.e. recon's value is something other than "black"), ignored otherwise

Name	Description
	Default is <none>, i.e., no message is displayed
spotted!	DML output flags to bang when a group is spotted. Flag is banged <i>in addition</i> to the module's global "prio!" flag. Uses the config zone's method.  <i>Only applies to prio zones</i> (ignored when blacklist zone) Defaults to <none>
silent	Only applicable to priority groups. When present and set to true, the recon report and map mark are suppressed for any groups defined with this zone. Note that this does NOT apply to any prioMessage you have defined for this zone, as that will still be displayed. Defaults to false

## Supports DML Flags

### Config Zone Settings

Name	Description
verbose	A value of "true" turns on debugging messages. Default is "false"
autoRecon	If true, all planes are automatically treated as actively reconnoitering.  <b>NOTE</b> This is on by default. To avoid excessive scouting activity, you should reduce the number of active scout planes with enabling or disabling one of the following attributes: redScouts (off), blueScouts (off), greyScouts (off), playerOnlyRecon (on) Default: true
redScouts	If true, all red planes are included as scouts when autoRecon is true. Default is false
blueScouts	If true, all blue planes are included as scouts when autoRecon is true. Default is <b>true</b>
greyScouts	If true, all neutral planes are included as scouts when autoRecon is true. Default is false
playerOnlyRecon	If true, only player aircraft are included as scouts when autoRecon is true. All planes will not be automatically included as scouts.  <b>IMPORTANT</b> This condition is applied <b>in addition</b> to blueScouts and redScouts. If you disallow red scouts, red players will not automatically be added to the list of scouts. Defaults to false
reportNumbers	If true, the F10 map markings include a unit count of the group at the time the group was discovered. Default is true
applyMarks	If true, discovered groups are marked on the F10 map. Default is true
announcer	If true, discovered groups are announced via text. Default is true
detectionMinRange	The detection range of a recon plane under worst conditions (low-level flying). Default is 3000 (3 km)
detectionMaxRange	The detection range of a recon plane under best conditions (high-altitude). Default is 12000 (12 km)

<b>Name</b>	<b>Description</b>
maxAlt	The altitude at which a plane achieves maxDetectionRange. Default is 9000 (9 km, 27'000 ft)
prio+	A flag in ME that is increased every time that a priority unit is detected
detect+	A flag in ME that is increased every time that a normal (non-priority) is detected
reconSound	The name of the sound file to play when e recon event occurs. Defaults to <nosound>, which will not play a sound
autoRemove	When a detected group is destroyed, that group's mark is immediately removed from the map if this attribute is set to true Defaults to true
mgrs	Defines if the location of the group that is detected is given in Lat/Lon (default) or MGRS. Set to true to enable MGRS. Default is false (coordinates are displayed in Lat/Lon)
activate? on?	Watchflag to monitor for a change. If a change is detected, Recon Mode goes into active state. Defaults to <none>
deactivate? off?	Watchflag to monitor for a change. If a change is detected, Recon Mode turns off Defaults to <none>
active	Set to false to start Recon Mode in disabled (off) state. Defaults to true (Recon Mode enabled)
reportTime	Number of seconds that a recon message stays on the screen. Defaults to 30.

**Supports Watchflags**  
**Supports DML Flags**  
**Supports zone-local verbosity**

## 32.4 Demos

- Recon Mode
- Recon Mode - Reloaded

## 33 rnd Flags

### 33.1 Summary

Can randomly set flags – from a pool of flags, in many different methods

### 33.2 Dependencies

dcsCommon, cfxZones

### 33.3 ME Integration

Name	Description
<b>RND!</b>	Marks this as a randomizer.  Set of flags, as a comma (',') separated list of the flag names that can be chosen from. The flag names can appear in any sequence. Supports ranges like "2-7" (ME numbers only). Flag names can be included multiple times, including the same flag name multiple times simply increases the likelihood that this number is chosen. Examples: "2, 4, A, A, F, 6" "A9, 3-18, C33, samAttack, 11-11"  <b>MANDATORY</b>
method rndMethod	Describes how flags are to be set. Follows standard DML flag method. <b>Defaults to "inc"</b>
pollSize	Number of items to choose from the set of flags during a cycle. Can be a range: two numbers separated by a hyphen, e.g. "2-5". When a range is given, pollSize is randomized each cycle to a number between the lower and upper bounds, inclusive. Defaults to 1
remove	When set to true, the flags that were chosen during a cycle are removed from the set of flags. Defaults to false.
reshuffle	When set, the original full set of flags is restored when all flags have been removed. Defaults to false
f? in? rndPoll?	DML Watchflag to start a random cycle. Defaults to <none set> You can use any synonym, but only one per Zone
triggerMethod rndTriggerMethod	Watchflag condition when to trigger. Defaults to "change"
onStart	If true, a cycle is run for this randomizer 0.25 seconds after the mission starts. Defaults to false  <b>NOTE:</b> if no f? (or synonym) is specified, and onStart is false, the randomizer will never activate. You'll receive a warning.



Name	Description
<del>done+1</del> done! rndDone!	The flag number to bang! when the randomizer has run out of flags to change, and reshuffle is false (randomizer did nothing) Is banged! every time that the randomizer runs a cycle on an empty flag set

**Supports DML Flags**

**Supports DML Watchflags**

**Supports zone-local verbosity**

## 33.4 Demos

- Random Glory
- Random Death
- Pulsing Fun
- Attack of the CloneZ

## 34 Smoke Zones

### 34.1 Summary

Places a colored permanently refreshing smoke at the center of the zone

### 34.2 Dependencies

dcCommon, cfxZones

### 34.3 ME Integration

Name	Description
smoke	Adds a permanent smoke affect to the center of the zone. Possible values for the smoke effect are: <ul style="list-style-type: none"><li>• “green” or “0”</li><li>• “red” or “1”</li><li>• “white” or “2”</li><li>• “orange” or “3”</li><li>• “blue” or “4”</li><li>• “random”, “?” or “rnd” (random color from above)</li></ul> <b>MANDATORY</b>
paused	When true, will not start smoke at mission start, but wait for a signal on the f? flag. Defaults to false (smoke starts at mission beginning). Note that if you set paused to true and omit the f? attribute, you can only start this smoke via API
f? startSmoke?	Watchflag. When this flag triggers, smoke starts. Defaults to <none>
altitude	Altitude (in meters) above ground that the smoke should be created. Defaults to 1m
triggerMethod smokeTriggerMethod	Conditions when the DML Watchflag should trigger Defaults to ‘change’

### Supports Watchlags

### 34.4 Demos

- Smoke'em DML Intro
- Random Glory
- Once, twice, three times a maybe

## 35 Spawn Zones

### 35.1 Summary

Allows spawning of ground units based on the types attribute (text)

### 35.2 Dependencies

dcsCommon, cfxZones, cfxCommander, cfxGroundTroops, (Helo Troops)

### 35.3 ME Integration

Name	Description
spawner	Marks this ME Zone as a spawn zone. <b>Value of this attribute is ignored</b> , use it to describe what it spawns to make mission editor easier for you <b>MANDATORY</b>
f? spawn? spawnUnits?	Flag (ME-compatible) to observe. Each time the value of that flag changes, a new spawn is forced, ignoring all other settings like maxSpawn, cooldown, paused, etc. Defaults to no flag to observe Use only one synonym per zone
pause?	Flag to observe. Each time the flag's value changes, the spawner's 'paused' setting is forced to 'true'. Used to 'pause a spawner
activate?	Flag to observe. Each time the flag's value changes, the spawner's 'paused' setting is forced to 'false'. Used to 'activate' a paused spawn
types	Type string array for the ground units that are spawned. Example "Roland ADS, Roland Radar, Roland ADS" or "Soldier M4" – <b>WARNING:</b> Blanks are part of the type, and blanks before and after the last character are automatically stripped. For a full reference of objects and their types, see here <a href="https://github.com/mrSkortch/DCS-miscScripts/tree/master/ObjectDB">https://github.com/mrSkortch/DCS-miscScripts/tree/master/ObjectDB</a> and use whatever is given as value for the "typeName" attribute, e.g. "Soldier M249" for the "INF Soldier M249.lua"
country	The country (a number) the units that spawn belong to, e.g. "22" for Switzerland ( <b>Warning:</b> unlike many other zone extensions, we use a County, not a Coalition here. The coalition is determined by which Faction the country belongs to as is defined when you create the mission, or by using the faction editor. Common Countries are Russia = 0, Ukraine = 1, USA = 2, UN Peace Keepers = 82 You can find a reference of all country codes here: <a href="https://wiki.hoggitworld.com/view/DCS_enum_country">https://wiki.hoggitworld.com/view/DCS_enum_country</a> ).
masterOwner	A string that references another ME Zone by name. It must match that Zone's name exactly, and that zone must have an owner (e.g. defined as an cfxOwnedZone or FARPZone). A spawner only spawns automatically when the masterOwner's owning faction is the same as the spawner's country affiliation. On the map, the spawner does not have to be inside the masterOwner's zone, it can be hundreds of miles away. You can use this to start spawning reinforcements in a

Name	Description
	completely unrelated part of the map when units conquer the masterOwner zone. If no masterOwner is specified, the Spawner spawns as directed and disregards any surrounding zones that happen to be owned Optional, defaults to empty
baseName	A name (e.g. "Hill Marines") that is used to create units and groups from during unit spawning. <b>If provided, baseName MUST BE UNIQUE. If you do not assign a base name, a unique one will be generated for you.</b> If two spawners have the same baseName, one of them will not spawn, so if for some reason a spawner does not spawn, make it a habit to check this first.
cooldown	Time interval (in seconds) from when a new group can be produced (removed from the spawner) to the moment it is produced. Defaults to 60
autoRemove	Usually, a spawner retains ownership of a group that is produced, and will re-start the spawning cycle only after it was removed. If you add the autoRemove attribute with a "yes" or "true" value, the Spawner will automatically re-start the spawning cycle (cooldown, produce) as soon as the new group has spawned. You can use this to automatically give orders and have units move out after they have spawned (similar to how OwnedZones spawn attackers). Be advised that you can create a lot of vehicles on your map in a very short time, so be careful when using autoRemove. Defaults to 'false'
heading	The direction the spawned group is oriented to, from the center of the spawn zone. Defaults to 0
formation	Formation of the spawned group. See dcsCommon for supported group formations. Defaults to 'circle out'.
paused	When paused, a spawner only spawns when other scripts tell it to (e.g. your own scripts, cfxHeloTroops, triggers). Defaults to "no"
orders	This is an optional interface to other troop-governing modules, e.g. cfxGroundTroops. Default is "guard", and spawners support in addition to those that cfxGroundTroops support
range	An attribute used to pass a range value to orders (e.g. JTAC laze range, detection/engage range)
target	An attribute used to pass a target zone when used in conjunction with the 'attackZone' orders
maxSpawns	The maximum number of times that this spawner spawns groups. Set it to a positive number (e.g. 3) to spawn that many times. Set it to a negative number for an unlimited number of spawns (default is -1). Set it to zero (0) and the spawner will never spawn.
requestable	Interfaces with other scripts, if you set this value to true, troops will only spawn on request via <code>cfxSpawnZones.spawnWithSpawner()</code> . See the API section on how to get a list of eligible spawners. Automatically interfaces with HeloTroops and other enhancements
trackWith:	List of groupTracker zones. All spawned groups are added to these groupTrackers. If you have stacked the tracker on the same zone as the spawner, you can use a single asterisk '*' as zone name. Supports a comma-separated list of trackers if you simultaneously want to pass the spawned groups to multiple trackers

Name	Description
	Defaults to <None>

## 35.4 Demos

- Random Death
- Moving Spawners
- Moving Spawners II
- Helo Troops

## 36 unGrief

### 36.1 Summary

Module to deter griefers and enforce PVE-only rules

### 36.2 Dependencies

dcsCommon, cfxZones

(SSB on server when using SSB as retaliation)

### 36.3 ME Integration

unGrief uses a config zone to control the module's main functionality

Name	Description
verbose	A value of "true" turns on debugging messages. Default is "false"
graceKills	Number of own faction ("friendly") kills that are permissible before unGrief retaliates. Set to 0 to disallow (and immediately punish) any friendly fire kills. Default is 1
retaliation	How unGrief retaliates towards the player when their graceKills are exceeded. The following options are supported: <ul style="list-style-type: none"><li>• 'boom' Place a small explosive inside the plane, grin, ignite.</li><li>• 'ssb' Use server-side SSB to kick the player from the plane</li></ul> Default is 'boom'
wrathful	Sometimes griefers are slow learners. When set to true, unGrief disallows a repeat offender to re-slot after their second transgression. Their plane is destroyed every time they try to slot until the mission ends.
pve pveOnly	When set to true, PVE rules are in force for this mission. Player versus Player kills count like friendly kills Defaults to FALSE (PVP killing is allowed)
ignoreAI	Ignores friendly kills if the killed unit was AI-controlled (i.e. not a player unit). Useful in conjunction with PVE rules. Defaults to false.
warnings	When set to true, players entering and leaving a PvP zone receive a notification. Only works when PVE is set to true Defaults to true (notifications when entering/leaving a PVP zone)

You can designate areas as PvP combat zones (requires that pve is enabled)

Name	Description
pvp	The mere presence of this attribute marks this zone as a PVP combat zone. Killing players of another faction in this zone is legal. Same-faction kills are still illegal and will be punished.
strict	When set to true enforces 'strict' pvp rules, requiring both planes be inside the PvP zone at the time of the kill. When false, only the killed player plane must be inside the PvP zone. Defaults to false

## 36.4 Demos

- Good Grief
- The Danger Zone

## **37 Unit Persistence**

### **37.1 Summary**

Module that provides persistence (load & save) ability for ground units and static objects that are placed with ME (i.e. it does not supports units that are spawned dynamically)

### **37.2 Dependencies**

Requires dcsCommon, cfxZones, persistence and cfxMX.

### **37.3 ME Integration**

### **37.4 Demos**

- Being Persistent



## 38 Unit Zone

### 38.1 Summary

Tests if a player unit or any member of an AI group is inside/outside a zone and can change flags when the status changes.

### 38.2 Dependencies

dcsCommon, cfxZones

### 38.3 ME Integration

Name	Description
unitZone	Marks this ME Zone as an anchor for unitZone <b>MANDATORY</b>
lookFor	<p>Name for the AI group or player unit to check zone status. If the last character in the name is an asterisk "*", exact matches <i>and</i> all group/unit names that start with that string (minus asterisk) are accepted, e.g. if you supply "Hel*" all of the following would be accepted:</p> <ul style="list-style-type: none"><li>• Hel</li><li>• Hello World</li><li>• Helo Rescue-1</li><li>• Hellfire</li></ul> <p>You can use this feature to your advantage in conjunction with cloners or spawners, as these all produce groups with a known base name.</p> <p>If you only supplied "Hel", only (without the asterisk "*") only the group whose name exactly matches "Hel" is checked.</p>
matching	<p>What type of units to match. Currently supported are</p> <ul style="list-style-type: none"><li>• group (default): look for group names</li><li>• player – look only at player units and match their unit's (not group's) name against lookFor</li></ul> <p>Default: group</p>
coalition uzCoalition	<p>The coalition (red/blue) units to check. Accepts 0, 1, 2, red, blue, neutral. Note that 0 (zero) and 'neutral' means 'both' in this case, neutral groups/units are never checked against the zone</p> <p>Defaults to 0 (both)</p>
filterFor	<p>Which categories to look for. If no attribute is given, <b>all</b> categories are checked against the zone (when their name pattern matches). When you supply a filterFor attribute, only that category is considered. Currently supported are</p> <ul style="list-style-type: none"><li>• 0 (zero) or "aircraft" or "air"</li><li>• 1 or "helo" or "heli2" or "helicopter"</li><li>• 2 or "ground"</li><li>• 3 or "ship"</li></ul>

Name	Description
	<ul style="list-style-type: none"> <li>• 4 or “train”</li> </ul> <p>Defaults to no filtering</p>
enterZone!	Change this flag when the first unit (player) or part of all groups that match the criteria enters the zone
exitZone!	Change this flag when the last unit (player) of all groups that match the criteria have exited the zone (being destroyed counts as leaving)
changeZone!	Changes this flag whenever enterZone! or exitZone! are triggered
method uzMethod	DML Flag method for output. Use only one synonym per zone
uzOff?	Watchflag. When triggered, this zone will no longer perform checks. When already off, nothing happens
uzOn?	Watchflag. When triggered, this zone will resume checks. When already on, nothing happens
triggerMethod uzTriggerMethod	Method that determines when the watchflags should trigger. Default is “change”
uzDirect	When present, this flag (or flags) is always set to the current state of the unit zone: <ul style="list-style-type: none"> <li>• 1 when one or more units in the zone</li> <li>• 0 when none of the indicated units in the zone.</li> </ul> <p>Default is &lt;none&gt;</p>
uzDirectInv	Like uzDirect, just inverted, provided since unitZones is often used to control many functions, and this saves an inverter (changer) module: <ul style="list-style-type: none"> <li>• 0 when one or more units in the zone</li> <li>• 1 when none of the indicated units in the zone.</li> </ul> <p>Default is &lt;none&gt;</p>

**Supports DML Flags**  
**Supports Watchflags**  
**Supports zone-local verbose**

## 38.4 Demos

- Follow Me!
- xFlags – Field Day
- Gate and Switch
- Forever-looping Spawners

## 39 Wiper

### 39.1 Summary

Removes objects inside a zone whenever you trigger it

### 39.2 Dependencies

dcsCommon, cfxZones

### 39.3 ME Integration

Name	Description
wipe?	Watchflag. Triggers a wipe cycle  <b>MANDATORY</b>
triggerMethod triggerWiperMethod	Method that triggers the Watchflag
category wiperCat	Category of the objects that are affected by the wipe (i.e. if they belong to the category they may be wiped). Possible values are <ul style="list-style-type: none"><li>• “unit” or 1</li><li>• “weapon” or 2</li><li>• “static” or 3</li><li>• “base” or 4</li><li>• “scenery” or 5</li><li>• “cargo” or 6</li></ul> Defaults to ‘static’
wipeNamed	<i>Optional</i> comma-separated name list that an object’s name must match in order to be wiped. Supports an asterisk (“*”) as wildcard to match anything. For example, “Ba*” would match “Base”, “Ba”, “Babushka”, and “Bathyscape”  <b>Examples:</b> <ul style="list-style-type: none"><li>• “Ba*” – all objects inside the zone whose name starts with “Ba”</li><li>• “Grou*, Commander Kirk, He*” – all objects whose name starts with “Grou” or “He”, and the object whose name exactly matches “Commander Kirk”</li></ul> Defaults to <option off>, no name filtering
wipeInventory	A Boolean that turns on the wiper’s inventory function. Whenever triggered, the zone lists all objects, it finds inside the zone, sorted by category. Note that there may be objects inside a zone that wiper cannot find, and that it may return objects that are not really inside the zone. Both are a DCS limitation, not a bug in wiper.

**Supports DML Flags**

**Supports DML Watchflags**

## 39.4 Demos

- Viper with a double you

## 40 xFlags (Flag Testing)

### 40.1 Summary

This requires that multiple input flags meet certain conditions to trigger the output flag. xFlags first applies the trigger method to evaluate input flags individually, and then requires that the individual results meet a condition to arrive at a final results. For example, it can be used to determine if ALL flags (requirement) have individual values of ">2" (individual trigger)

### 40.2 Dependencies

dcsCommon, cfxZones

### 40.3 ME Integration

Name	Description
xFlags?	<p>A list (comma-separated) of input flags whose values should be evaluated to form the output signal</p> <p><b>MANDATORY</b></p>
require	<p>Condition/Operation that should apply to the input flags to form the output value. Currently supports the following conditions:</p> <ul style="list-style-type: none"><li>• 'or', 'any', or 'some' triggers if at least one of the input flags has triggered</li><li>• 'and' or 'all' triggers if all the input flags have triggered</li><li>• 'more than' triggers if more than the value given in '#hits' of input flags have triggered</li><li>• 'at least' triggers if #hits or more of the input flags have triggered</li><li>• 'exactly' if triggers if the number of input flags that have triggered is equal to #hits</li><li>• 'none' triggers if none of the input flags have triggered. Requires that you turn off one-shot mode</li><li>• 'not all' or 'nand' triggers when not all input flags have triggered. Requires that you turn off one-shot mode</li></ul>

Name	Description
	<ul style="list-style-type: none"> <li>• 'most' triggers when more than half of the input flags have triggered. Will not trigger if exactly half have triggered, so be careful if the number of input flags is even.</li> <li>• 'half or more' triggers when half or more of the input flags have triggered. Will also trigger if exactly half of all flags have triggered</li> <li>• 'never' used when you are using xFlag's "direct outputs" (xDirect, xCount, xChange) and want it to operate during the entire mission. xFlags will never trigger xSuccess, and keep evaluating, setting xDirect, xCount and xChange accordingly</li> </ul> <p>Defaults to 'some'</p>
#hits	<p>Value used for only some of the require attribute. Can be a value or flag name (in which case the value will be loaded from that flag). Numbered flags must be enclosed in double quotes, e.g. "22" to access flag 22. Defaults to 1 (one)</p>
xFlagMethod	<p>Condition that must be met for individual input flags. Is identical to trigger method for Watchflags except it is applied to each input flag individually. Defaults to "change"</p>
xSuccess! out!	<p>Flag to bang! when xFlags when the evaluation of input flags succeeds (all conditions are met). Once xSuccess is triggered, and unless oneShot is set to false, this zone's xFlag pauses until xReset is triggered. Defaults to &lt;none&gt;</p>
xChange!	<p>Flag to bang! when xFlags detects a change in the input configuration. Merely detects a change in the input configuration, has no relation with xSuccess!, except that xSuccess will also be accompanied by a bang on xChange! Defaults to &lt;none&gt;</p>
xDirect	<p>Each time xFlags evaluates the input flags, it directly sets the xDirect flag to the evaluation result (0 or 1) – this is different from what xSuccess may output, since that flag's value is dependent on the xMethod attribute.</p> <p><b>This flags value is set directly, not via DML method.</b></p> <p>Defaults to &lt;none&gt;</p>
xCount	<p>Each time xFlags evaluates the input flags, it directly sets the xDirect flag to the number of hits (positive test results from the individual flags tests). For example, if three tests of the input flags are successful, xFlags sets the value of this output to the number 3</p> <p><b>This flags value is set directly, not via DML method.</b></p> <p>Defaults to &lt;none&gt;</p>
xReset?	<p>When the value of this input changes, the zone's xFlag module is reset, and evaluation starts afresh.</p>

Name	Description
	<b>Note: this input always reacts to a change in the flag's value</b> Defaults to <none>
method xMethod	DML method for output flags Defaults to "inc"
oneShot	When the value if this attribute is false, that zone's xFlag module will not stop evaluating after it triggers xSuccess.
xOff?	Flag to turn the xFlag off, suspending it. When turned off, no processing of input flag occurs. The xFlag will still respond to xReset by loading a new zero state. <b>Note: this input always reacts to a change in the flag's value</b> Defaults to <none>
xOn?	Turns a suspended xFlag back on to resume processing. It resumes processing where it left off <b>Note: this input always reacts to a change in the flag's value</b> Defaults to <none>
xSuspended	Sets the initial state of xFlag. Setting it to true suspends the xFlag at mission start Defaults to false

Supports DML Flags  
 Supports DML Watchflags  
 Supports zone-local verbose

## 40.4 Demos

- xFlags – Field Day
- Count Base's Blues

## 41 Module Name

### 41.1 Summary

### 41.2 Dependencies

### 41.3 ME Integration

### 41.4 Demos